



Clearing Your Web Browser

Clearing your web browser's cache, cookies, and history may remove data such as the following:

- Saved passwords
- Address bar predictions

Chrome

1. In the browser bar, enter: `chrome://settings/clearBrowserData`.
2. At the top of the Clear browsing data window, click Advanced.
3. Select the following:
 - a. Browsing history
 - b. Download history
 - c. Cookies and other site data
 - d. Cached images and files
 - e. From the Time range drop-down menu, you can choose the period of time for which you want to clear cached information. To clear your entire cache, select All time.
4. Click CLEAR DATA.
5. Exit/quit all browser windows and re-open the browser.

Firefox

1. From the History menu, select Clear Recent History. If the menu bar is hidden, press Alt to make it visible.
2. From the Time range to clear: drop-down menu, select the desired range; to clear your entire cache, select Everything.



3. Next to Details, click the down arrow to choose which elements of the history to clear; to clear your entire cache, select all items.
4. Click Clear Now.
5. Exit/quit all browser windows and re-open the browser.

Microsoft Edge

1. In the top right, click the Hub icon (looks like star with three horizontal lines).
2. Click the History icon (looks like a clock), and then select Clear all history.
3. Select Browsing history, then Cookies and saved website data, and then Cached data and files. Click Clear.
4. After the All Clear! message appears, exit/quit all browser windows and re-open the browser.

Internet Explorer 11

1. Select Tools > Internet Options > Delete browsing history. If the menu bar is hidden, press Alt to make it visible.
2. Deselect Preserve Favorites website data, and select:
 - Temporary Internet files or Temporary Internet files and website files
 - Cookies or Cookies and website data
 - History
3. Click Delete. You will see a confirmation at the bottom of the window when the process is complete.
4. Under Settings > Temporary Internet files, select Every time I visit the webpage.
5. Exit/quit all browser windows and re-open the browser.



Opera

1. From the Opera menu, select Settings, then Privacy & Security, and then Clear browsing data.
2. In the dialog box that opens, from the Obliterate the following items from: drop-down menu, select The beginning of time.
3. Select the following:
 - Browsing history
 - Download history
 - Cookies and other site data
 - Cached images and files
4. Click Clear browsing data.
5. Exit/quit all browser windows and re-open the browser.

Safari 8 and later

1. From the Safari menu, select Clear History or Clear History and Website Data.
2. Select the desired time range, and then click Clear History.
3. Go to Safari > Quit Safari or press Command-Q to exit the browser completely.